Install Windows Media Player

MFP = DISM / Online / Get-Capabilities | findstr "MediaFeaturePack"; MFPack = MFP.split(":")[1].replace(" ", ""); DISM / Online / Add-Capability / CapabilityName: MFPack / NoRestart

Check Windows Media Player

Get-WindowsCapability -online | Where-Object -Property name -like "*WindowsMediaPlayer*"

Install Media Feature Pack

\$WMP = DISM /Online /Get-Capabilities | findstr "WindowsMediaPlayer";\$WMPPkg = \$WMP.split(":")[1].replace(" ", "");DISM /Online /Add-Capability y /CapabilityName:\$WMPPkg /NoRestart

Check Media Feature Pack

Get-WindowsCapability -online | Where-Object -Property name -like "*MediaFeaturePack*"

Install Additional Features

IMPORTANT

All Eight of the following Microsoft Store Apps need to be Installed, as they contain necessary Audio & Video Codecs, that are Required by the "Windows Media Player" Software and other Applications that utilize the Audio, Video and Camera Features.

VP9 Video Extensions

winget install --name "VP9 Video Extensions" --source msstore --accept-source-agreements --accept-package-agreements

Web Media Extensions

winget install --name "Web Media Extensions" --source msstore --accept-source-agreements --accept-package-agreements

HEIF Image Extensions

winget install --name "HEIF Image Extensions" --source msstore --accept-source-agreements --accept-package-agreements

Skype:

winget install Skype --source msstore --accept-source-agreements --accept-package-agreements

Movies & TV:

winget install --name "Movies & TV" --source msstore --accept-source-agreements --accept-package-agreements

Windows Media Player:

winget install --name "Windows Media Player" --source msstore --accept-source-agreements --accept-package-agreements

Xbox Game Bar:

winget install --name "Xbox Game Bar" --source msstore --accept-source-agreements --accept-package-agreements

Windows Voice Recorder:

winget install --name "Windows Sound Recorder" --source msstore --accept-source-agreements --accept-package-agreements

IMPORTANT: After Installing the "Windows Media Player", "Media Feature Pack" and All Eight of the " Additional Features" (Microsoft Store Apps), the Computer will need to be Restarted in order to Complete the Last Step of the Installation Process.